

# PROGRAM FILE



## Memotech MTX PANEL Fill Amendment

by Harrie Wijnands

This listing gives some changes and refer to that for instructions and use. improvements to the utility published in 'Program File', PCW June. Please are the important changes.

```
10 CODE
● 4007 IMPFIL: LD DE,#F6F0      ;point to where we are
● 400A LD (#FA92),DE      ;change stack limit
● 400E LD (#FA9F),DE      ;change panel expand bytes
● 4012 LD HL,FILL ;point to the start
● 4015 LD BC,#29 ;how many bytes to move
● 4018 LDIR ;move them !
● 401A LD A,#C3 ;set up jump to fill
● 401C LD (#FA9E),A
● 401F RET
● 4020 FILL: LD A,(#FD7D) ;was the last character a "F" ?
● 4023 CP "F"
● 4025 RET NZ ;if not return
● 4026 RST 28 ;print "Fill" and get bytes
● 4027 DB #AB
● 4028 DB "Fil",#EC ;last byte has bit 7 set
● 402C PUSH BC ;save the start address on stack
● 402D RST 28 ;print "To" and get bytes
● 402E DB #AB
● 402F DB "T",#EF ;last byte has bit 7 set
● 4031 PUSH BC ;save the end address on stack
● 4032 RST 28 ;print "With" and get byte
● 4033 DB #AB
● 4034 DB "Wit",#EB ;last byte has bit 7 set
● 4038 LD A,C ;fetch the byte into A
● 4039 POP HL ;get the end address
● 403A POP DE ;get the start address
● 403B AND A ;clear carry flag
● 403C SBC HL,DE ;calculate how many bytes
● 403E RET C ;don't fill if end address below start address
● 403F LD (DE),A ;fill the first byte
● 4040 RET Z ;only one byte to fill if zero length
● 4041 LD B,H ;set up length in BC
● 4042 LD C,L
● 4043 LD H,D ;set up start address in HL
● 4044 LD L,E
● 4045 INC DE ;point to the next byte with DE
● 4046 LDIR ;fill the rest
● 4048 RET
```

Symbols:

FILL 4020 IMPFIL 4007